
BASIC TURBAN

SEWING INSTRUCTIONS

1.5cm seam allowance

- 1. Stitch darts
- 2. Fold in half, right sides together, matching darts.
- 3. Stitch curved seam with 1.5cm seam allowance from * to *, starting 2cm in from centre fold and folding dart seams away from centre fold.



4. Open seam (do not press). Stitch seam allowance down on either side of this seam to form two casings.

To make front tab

- 5. Cut a piece of fabric approximately 5cm x 12cm. Fold right sides together to form a 2.5cm x 12cm tube. Stitch with a 5mm seam allowance, turn through and press with seam running down centre back.
- 6. Cut a piece of ribbon approximately 22cm long. Thread through the two casings starting at centre back fold. TIP: Attach a safety pin to the end of each ribbon and thread them through at the same time.
- 7. Before pulling up tight, tuck the end of the front tab through the hole at the centre back. Pull ribbon ends out and machine across ends to secure.
- 8. Push gathers away from the lower edge, turn up a 2.5cm to 3cm hem and zig-zag stitch.
- 9. Adjust tab, cut to length and stitch lower end in place. On inside, secure top end of tab.